

Digital Scrapper Tutorials



Type Overlay

by Linda Sattgast

A type overlay adds a wonderful, artistic look to your layout. Use it over the entire background paper or use bits and pieces of it for artistic effect.



Prepare the Type Overlay

- Download the Type Overlay.psd file provided with this tutorial and open it in your program.
- If you get a warning that your program doesn't support the font, that's OK. Just choose a different font that's already on your computer. Even if you have this font, you can choose a different font that matches the mood of your page. Simply get the Type tool and choose a different font.

Apply the Type Overlay

- Open a scrapbook page, and in the Layers panel, select the layer where you want the Type Overlay to land.
- Make the Type Overlay document active.
- Press the Shift key and click and drag the type layer from the Layers panel onto your scrapbook page.
- Press Alt (Mac: Opt) and click on the Layer Mask icon on the Layers panel. This will make the type layer disappear. (If your version of Photoshop Elements doesn't have layer mask capabilities, download a layer mask workaround. <http://www.digitalscrapper.com/downloads/layer-mask-workaround.zip>)

Adjust the Type Overlay

- Get the Brush tool.
- In the Options Bar, open the Brush Picker and choose a large, soft brush.
- In the Options Bar, lower the opacity to 10 percent or less.
- If you want your brush to be larger or smaller, press the right or left Bracket keys.
- Make sure the black Layer Mask thumbnail is selected in the Layers panel. It will have corner frames around it if it's selected.
- Make sure white is the Foreground color. If it isn't click on the curved double arrow icon next to the Color Chips.
- Brush on your page wherever you want the type to appear.

Link to the Video Lesson:

<http://www.digitalscrapper.com/members/video-plus/20videos-type/16-type-overlay.html>

Credits:

Page by Linda Sattgast

Photos by Rachel Hadiashar and Allison Sattgast

Kit: Recollection by Joanne Brisebois, photo mask by Linda Sattgast

Fonts: Century Gothic, P22 Typewriter, P22 Cezanne

Terms of Use

Digital Scrapper Type Video by Linda Sattgast

© 2012 by Digital Scrapper

YOU MAY:

: use these videos and step-by-step manuals for your own personal use to learn digital scrapbooking skills.

YOU MAY NOT:

- : claim the Digital Scrapper Premier videos and manuals as your own.
- : share or redistribute the videos and manuals in any way, shape, or form—in person, electronically, or print, online or offline.
- : offer the videos or manuals for download, or otherwise include them in an email group or newsgroup for download or copying.
- : play the videos in group or school settings or share with others.

Thank you for complying with these terms of use!

Help Stop Software Piracy!